



# Artista

## Windows Drivers Updates Notes

Author:	tg1
Approved:	
Date:	07/12/10
Page	1 / 3

# Driver Update Notes

Monday July 12, 2010

The information given in this document is carefully checked and believed to be reliable. However, Distec takes no responsibility for any failure or product damage caused by the application of this information. Please check all connections carefully with the data sheet. Distec products are not intended for use in systems in which failures of product could result in personal injury. All mentioned trademarks are registered trademarks of their owner.

All specifications are subject to change without notification.

**flatpanel displays  
and solutions**

Data Display Group  
Augsburgerstr. 2b  
D - 82110 Germering  
Germany

Phone: +49 - (0)89/ 89 43 63 - 0  
Fax: +49 - (0)89/ 89 43 63 - 131  
E-Mail: [info@distec.de](mailto:info@distec.de)  
Internet: [www.distec.de](http://www.distec.de)

We support you worldwide with offices in Germany, Turkey, Great Britain and the USA.  
For further information contact your local distributor (see last page of this data sheet).



### ➔ Driver update from V1.4.x.xxxx up to V5.0.x.xxxx

Since the major version of the driver has changed, it will become necessary to entirely remove existing older drivers from the system in order to use the new driver.

This is done the following way:

- Remove every Artista device from the control PC.
  - Uninstall the previous ArtistaDisplay (Mainclass driver with desktop) driver
  - Uninstall the previous Mainclass driver
  - Uninstall the Netbus driver
  - Reboot the system after these steps!
  - Run the "ArtistaRegCleaner" from the V5.0.0.xxxx driver package.  
Reboot afterwards.  
(This step is essential in order to removed old driver registry entires!)
  - Install the new drivers as needed.
  - Connect now each device again to the system and go through the installation procedures.
-



DATA DISPLAY GROUP

Our company network supports you worldwide with offices in Germany, Turkey, Great Britain and the USA. For more information please contact:



DISTEC GmbH

**Distec GmbH**

Augsburger Str. 2b  
82110 Germering  
Germany

Phone: +49 (0)89 / 89 43 63-0  
Fax: +49 (0)89 / 89 43 63-131  
E-Mail: [info@distec.de](mailto:info@distec.de)  
Internet: [www.distec.de](http://www.distec.de)



DATA DISPLAY TEKNOLOJİ

**Data Display Teknoloji Elektronik San Ve Diş Tic A.Ş.**

Kustepe Leylak Sok.  
Nursanlar Is Merkezi  
Kat. 6 No: 21  
Sisli / Istanbul  
Turkey

Phone: +90 (0)212 / 356 04 20  
Fax: +90 (0)212 / 356 04 25  
E-Mail: [info@datadisplay.com.tr](mailto:info@datadisplay.com.tr)  
Internet: [www.datadisplay.com.tr](http://www.datadisplay.com.tr)




DISPLAY TECHNOLOGY

**Display Technology Ltd.**

A2 Spectrum Business Centre  
Anthonys Way, Medway City Estate  
Rochester, Kent, ME2 4NP  
United Kingdom

Phone: + 44 (0)1634 / 29 55 55  
Fax: + 44 (0)1634 / 29 55 43  
E-Mail: [info@displaytechnology.co.uk](mailto:info@displaytechnology.co.uk)  
Internet: [www.displaytechnology.co.uk](http://www.displaytechnology.co.uk)



A Data Display Company

**Apollo Display Technologies, Corp.**

85 Remington Blvd.  
Ronkonkoma, NY 11779  
United States of America

Phone: +1 631 / 580-43 60  
Fax: +1 631 / 580-43 70  
E-Mail: [info@apolloDisplays.com](mailto:info@apolloDisplays.com)  
Internet: [www.apolloDisplays.com](http://www.apolloDisplays.com)